

Export the parameters

Overview

This guide explains how to locate, filter, and export parameter groups from the CONTROL portal. You'll learn to navigate to the Parameters section, apply filters to find specific groups, and export the data in your preferred format.

Navigate to the Parameters Section

Begin by accessing the Parameters area within the Inventory module.

The screenshot shows the Zequence CONTROL admin portal. The sidebar on the left contains navigation options: Dashboard, Inventory (1), Parameters (2), Logs, Metrics, Groups, Scripts, Firmware, Locations, Files, Organization, Settings, and User log. The main content area is titled 'SELECT PARAMETER TO CHANGE' and shows a list of parameter groups. The table has columns: Name, Short-name / code, Group, Type, Active, Read-only, Notifications, and Organization. A search bar and a green funnel icon (4) are at the top right of the table. The footer shows '2024 © zequence Terms of service | Privacy policy | Changelog' and 'CONTROL admin portal v1.2.18'.

1. Click on **Inventory**
2. Click on **Parameters**
3. Click on **Parameters** again
4. Activate the filter by clicking the **green funnel icon**

Filter Parameters by Group

Once the filter panel is open, you can search for specific parameter groups.

The screenshot shows the Zequence CONTROL admin portal interface. The main area displays a table of parameter groups with columns for Name, Short-name / code, Group, Type, Active, Read-only, Notifications, and Organization. The 'FILTER' panel is open on the right, showing options for 'Records per page' (50 records), 'Group' (with a search input), 'Type', 'Active', 'Read-only', 'Notifications', and 'Organization'. A red circle '1' highlights the 'Group' field, and a red arrow points to it from the 'Number of clients' row in the main table.

1. The filter panel displays available filter options
2. Locate the **Group** field

Search for Your Group

The screenshot shows the Zequence CONTROL admin portal interface. The main area displays a table of parameter groups. The 'FILTER' panel is open on the right, showing options for 'Records per page' (50 records), 'Group' (with a search input containing 'Disco'), 'Active', 'Read-only', 'Notifications', and 'Organization'. The search results under 'Group' include 'Mikrotik hAP ac2 - Discovered' and 'Vendor Model [Base] - Discovered'. A red circle '1' highlights the search input, and a red circle '2' highlights the 'Vendor Model [Base] - Discovered' result.

1. In the **Group** field, enter a search term (e.g., type "Disco" to find all groups containing the word "Discovered")
2. Select your desired group from the results (e.g., "**Vendor Model [Base] - Discovered**")
3. Click the **Proceed** button to apply the filter

Verify Filtered Results

After applying the filter, confirm that the correct parameters are displayed.


The screenshot shows the 'PARAMETERS' section of the Zequence CONTROL admin portal. The page title is 'SELECT PARAMETER TO CHANGE'. The breadcrumb navigation is 'Home > Inventory > Parameters'. The page has tabs for 'Parameter groups', 'Parameters', 'Parameter options', and 'Validators'. The 'Parameters' tab is active. A search bar is at the top left. On the right, there are buttons for 'Import', 'Export', and '+ Add'. A red circle '3' is above the '+ Add' button. Below the search bar is a table with columns: Name, Short-name / code, Group, Type, Active, Read-only, Notifications, and Organization. The table lists various parameters such as 'Device', 'InterfaceStackNumberOfEntries', 'Bridging', etc. A filter dialog is open on the right side, showing 'Active filters' with 'Group' set to 'Vendor Model [Base] - Discovered'. A red circle '1' is next to the filter name. Below the filter, there are options for 'Records per page' (set to 50), 'Type' (set to 'Click for options'), 'Active' (set to 'All'), 'Read-only' (set to 'All'), and 'Notifications' (set to 'Click for options'). Buttons for 'Proceed' and 'Clear all' are at the bottom of the filter. At the bottom of the table, there is a pagination bar showing '1 2 3 4 ... Next > 7,326 results'. A red circle '2' is next to the '7,326 results' text. At the bottom left, there is a footer: '2024 © zequence Terms of service | Privacy policy | Changelog'. At the bottom right, there is a footer: 'CONTROL admin portal v1.2.18'.

1. Review the applied Group filter
2. Verify that the parameter count matches the expected number from your Profile (you can confirm the quantity by comparing it with the number of parameters Discovered in the Profile)
3. Proceed to export the parameters

Export the Parameters


Initiate the Export


Click the **Export** button to open the export dialog.



Select Export Format

Choose your preferred file format from the available options.






1. Select your desired format (e.g., **CSV**)
2. Click the **Export** button to start the export process

Download the Exported File


Monitor Export Progress

After initiating the export, a progress indicator appears at the top of your browser showing that the report is being generated.




Download Complete

When the export is ready, a download notification will appear.



Open the File

You can now open the exported CSV file to view your parameters.



Revision #4

Created 2026-02-13 22:19:07 UTC by ipena@zequence.com

Updated 2026-04-09 03:09:59 UTC by mauro@zequence.com